

Handbook
NIVUS DataHub Software Tool

NIVUS DataHub

Revised Manual

Document revision 02 / 15.10.2019
Original Manual: German, rev 02 as of 15.10.2019

NIVUS AG, Schweiz

Burgstrasse 28
CH - 8750 Glarus
Phone: +41 (0)55 6452066
Fax: +41 (0)55 6452014
swiss@nivus.com
www.nivus.de

NIVUS, Austria

Mühlbergstraße 33B
A - 3382 Loosdorf
Phone: +43 (0) 2754 567 63 21
Fax: +43 (0) 2754 567 63 20
austria@nivus.com
www.nivus.de

NIVUS Sp. z o.o., Polen

ul. Hutnicza 3 / B-18
PL - 81-212 Gdynia
Phone: +48 (0) 58 7602015
Fax: +48 (0) 58 7602014
biuro@nivus.pl
www.nivus.pl

NIVUS France

14, rue de la Paix
F - 67770 Sessenheim
Phone: +33 (0)388 9992 84
info@nivus.fr
www.nivus.fr

NIVUS U.K. Ltd., United Kingdom

Wedgewood Rugby Road
Weston under Wetherley
Royal Leamington Spa
CV33 9BW, Warwickshire
Phone: +44 (0)8445 3328 83
nivusUK@nivus.com
www.nivus.com

NIVUS Middle East (FZE)

Building Q 1-1 ap. 055
P.O. Box: 9217
Sharjah Airport International
Free Zone
Phone: +971 6 55 78 224
Fax: +971 6 55 78 225
middle-east@nivus.com
www.nivus.com

NIVUS Korea Co. Ltd.

#2502 M Dong, Technopark IT Center,
32 Song-do-gwa-hak-ro, Yeon-su-gu,
INCHEON, Korea 21984
Phone: +82 32 209 8588
Fax: +82 32 209 8590
korea@nivus.com
www.nivus.com

NIVUS Vietnam

21 Pho Duc Chinh, Ba Dinh
Hanoi, Vietnam
Phone: +84 12 0446 7724
vietnam@nivus.com
www.nivus.com

Copyrights and property rights

Translation

If the device is sold to a country in the European currency area, this instruction handbook must be translated into the language of the country in which the device is to be used. Should the translated text be unclear, the original instruction handbook (German) must be consulted or the manufacturer contacted for clarification.

Names

The use of general descriptive names, trade names, trademarks and the like in this handbook does not entitle the reader to assume they may be used freely by everyone. They are often protected registered trademarks even if not marked as such.

License Agreement

This software may be used in order to read out data from a maximum of 10 devices free of charge. The use of this software for more than 10 devices is subject to charge. Usage shall encompass the full or partial saving or copying of the software, the execution of the programs as well as the creation of an additional copy for backup purposes.

The software is provided under a license agreement. The license agreement specifies what you may do with the product and sets out the limitations of warranties as well as the damage compensation claims.

Read the license agreement carefully before you begin to work with the software.

It is not allowed to lend or hire the software in return for payment. Furthermore it is not allowed to sell the software to third persons.

It is not allowed to decompile, re-develop and disassemble the software or to implement any other modifications.

Copyright

No part of this publication may be reproduced, transmitted, sold or disclosed without prior permission. Damages will be claimed for violations.
All rights reserved.

Copyright© 2019

NIVUS GmbH. All rights reserved.
Im Taele 2
75031 Eppingen
Germany

Change History

Rev.	Date	Changes	Editor
02	15.10.2019	Branch Office NIVUS France (p. 2), Chap. 1.2 and Chap. 3	KG
01	19.12.2018	Addition Chap. 6	KG
00	27.11.2018	New document	KG

Table of Contents

Copyrights and property rights	3
Change History	4
Table of Contents	5
1 General Information	6
1.1 Notes to the User	6
1.2 Disclaimer.....	6
2 Basics	7
3 Installation	7
4 Start Screen	8
5 Basic Settings	9
5.1 Communication Hub.....	9
5.2 Device List.....	9
5.3 File Output.....	10
5.4 Options	10
5.5 FTP Exchange.....	11
5.6 SMTP Exchange	11
6 DebugLog	11

1 General Information



Important Note

- *Read carefully before use.*
 - *Keep in a safe place for later reference.*
-

Prior to installing or operating NIVUS DataHub read this software handbook carefully. Keep this software handbook in a place where it is accessible to all users at all times. This software handbook contains any information required for the intended use of the software.

Screenshots and Application Examples

All screenshots contained within this documentation are application examples. Depending on the operating system and the software version of the installed tools the representation may vary from the actual screen display.

1.1 Notes to the User

The software manufacturer is assuming that the reader/user is familiar with the basics of the operating system (Windows 7, Windows 8 or Windows 10) and in particular how to operate it. Basic control elements such as e.g. mouse, windows, buttons and similar will not be explained separately but knowledge about this is assumed.



Important Note

*The manufacturer is not responsible for faults, data loss or problems resulting from faulty knowledge about such basics.
The operator alone shall bear the associated risk.*



Important Note

*This manual is part of the software and must always be available for the user.
The safety instructions in the manual must be followed.*

1.2 Disclaimer

All legally associated companies and subsidiaries of NIVUS group assume no liability

- for damages owing to a change of this document. The legally associated companies and subsidiaries of NIVUS group reserve the right to change the contents of this document and this disclaimer at any time and without any notice.
- for any damages resulting from improper or inappropriate use.

2 Basics

The NIVUS DataHub is a communication program with simplified output of data. By using a server connection you can read out device data. Moreover, the data can be

- saved locally
- transmitted to FTP server
- transmitted via e-mail

as *.csv files or in Topkapi format

NIVUS DataHub supports the units below:

- NivuLink Micro
- NivuFlow Mobile

The Nivus DataHub can process data from several units simultaneously.

3 Installation


To order the NIVUS DataHub as ZIP file send an e-mail to datentechnik@nivus.com.

Install and open NIVUS DataHub

Procedure

1. Save ZIP file locally
2. Unzip the file
3. Open the unzipped directory
4. Double-click the NivusDataHubSetup_VerXXXX.exe installation file and follow the instructions on the screen
 - NIVUS DataHub installs and creates links in the start menu and on the desktop.
5. Open the "NIVUS DataHub" link
 - The NIVUS DataHub start screen opens.

4 Start Screen



- 1 **DebugLog** tab, description see chapter 6 *DebugLog*
- 2 **Basic settings** tab (here open), description see chapter 5 *Basic Settings*
- 3 Button **Connect**: connects to the Communication Hub
- 4 Button **Disconnect**: disconnects from Communication Hub

Fig. 4-1: Start screen

5 Basic Settings

In the **Basic Settings** tab you can find the options below:

- Communication Hub: server used for data transmission
- Device List: list of devices from which data are requested
- File Output: storage location and format of output files
- Options: start and minimising options of NIVUS DataHub
- FTP Exchange: options for storage of files on FTP server
- SMTP Exchange: options for sending files via E-Mail

5.1 Communication Hub


Configure the connection to Communication Hub here. Communication Hub is the server used for the transmission of data between device(s) and NIVUS DataHub.

The connection options can be found in the following table.

Field	Description	Remarks
Host	Input field for IP address or Communication Hub domain	Mandatory
Port	Input field for the port	Mandatory
Username	Input field for user name	Optional, specifications required only if Communication Hub has been set up accordingly.
Password	Input field for password	
Encryption	<input checked="" type="checkbox"/> : Connect to Communication Hub using the TLS 1.2 encryption protocol <input type="checkbox"/> : Connect to Communication Hub without extra encryption	If TLS encryption is active the Communication Hub must be configured for the encryption protocol as well.

5.2 Device List

Specify the devices from which data are to be requested here.




- 1 Input field for device names according to device configuration
- 2 Adds device (1) to the Device List
- 3 Removes selected device (4) from the Device List
- 4 Open Device List to select and then remove (3) a device

Fig. 5-1: Basic Settings: Device List Options

5.3 File Output

This menu is used to configure the file format as well as the file storage location. Files are saved in the current directory if no storage location is configured.



- 1 Input field for the separator (separating character in CSV-file).
Standard setting: ; (semicolon).
- 2 Open the file manager to navigate to the desired storage location.
- 3 Input field for the path directory where files are to be saved. In this directory NIVUS DataHub creates a subdirectory for each device.
- 4 : Data is saved in Topkapi format.
: Data is saved in CSV format.
- 5 The program sequence is saved in the **DebugLog** tab.
: The program sequence is saved in directory (3).

Fig. 5-2: Basic Settings: File Output Options

5.4 Options

Configure start and minimising options here.

Field	Description
Autoconnect	<input checked="" type="checkbox"/> : Connection to Communication Hub is made automatically on the start of the program. <input type="checkbox"/> : Connection to Communication Hub must be made manually after the program start using the Connect button.
Notify Icon	<input checked="" type="checkbox"/> : After minimising NIVUS DataHub is indicated only in the notification area of the task bar angezeigt. <input type="checkbox"/> : The NIVUS DataHub program icon remains to be in the task bar after minimising.

5.5 FTP Exchange

Optionally the files can be saved additionally on a FTP server automatically.

Specify the access data for the FTP server here:

Field	Description
Active	<input checked="" type="checkbox"/> : Files are saved on FTP server
Host	Input field for IP address or domain of the FTP servers
Port	Input field for the port
Username	Input field for the user name
Password	Input field for the password

5.6 SMTP Exchange

Optionally the files can be sent additionally via E-Mail automatically.

Specify the access data for the e-mail service here:

Field	Description
Active	<input checked="" type="checkbox"/> : Files are sent via e-mail
SSL	<input checked="" type="checkbox"/> : E-mails are transmitted using a SSL connection
Host	Input field for IP address or domain of the mail service
Port	Input field for the port of the mail service
Username	Input field for the user name of the mail account
Password	Input field for the password of the mail account
Mail From	Input field for the e-mail sender's address
Mail To	Input field for the e-mail recipient address

6 DebugLog

The following information the program sequence are recorded in the **DebugLog** tab.

Column	Options	Description
Date	-	Time stamp of record (system time).
Text	DataHub connected with [Login-ID]	Connection to Communication Hub was established sucessfully using the specified login ID.
	DataHub disconnected	Connection to Communication Hub was disconnected.
	Can not establish connection. Please check your settings.	Connection to Communication Hub cannot be established. Verify settings.
	Added Historical values for [Device-ID] to [Time Stamp/Time Range]	Data recorded including the device ID and the time stamp of the data point or including the data range (UTC).

This information can be saved optionally, see chapter *5.3 File Output*.